Deutsche Sauna-Akademie®	**Deutsche Sauna-Akademie**
Titel	How Do Sauna, Steam, Infrared and Water Baths Heat the Body?
Subtitel	A comparison of heat flow, humidity, radiation, evaporation and the actual thermal load
Author	Dr. Karsten Gröning
Published by	International Sauna Academy | Sauna Library

Short answer: The temperature of a bath does not tell us how much heat reaches the body. A Finnish sauna may have the highest air temperature, yet dry air still allows substantial evaporative heat loss. In a humid warm-air bath, evaporation is progressively restricted. In a steam bath, saturated air can additionally transfer latent heat by condensation on the cooler skin. Infrared cabins deliver a larger share of their heat directly by radiation, while warm water surrounds most of the body with a medium that transfers heat far more effectively than air and prevents evaporative cooling of the immersed skin. The decisive variable is therefore the net heat flow into the body: incoming convection, radiation, conduction and condensation minus outgoing evaporation and other heat losses.

A 100 °C sauna, a 50 °C humid warm-air bath, a 42 °C steam bath, an infrared cabin and a 40 °C water bath can all make a person hot. Yet they do so by very different physical mechanisms. Comparing them only by temperature is therefore misleading. The body does not respond to the number on the thermometer; it responds to the balance of heat flowing toward and away from the skin.

This distinction is central to the scientific understanding of thermal bathing. The same skin temperature can be exposed to hot dry air, saturated steam, infrared radiation or warm water, but the resulting heat flux can differ greatly because air, water and radiation transport energy in different ways. [1–5]

The heat balance of the bather

The thermal state of the body can be described as a heat balance. Metabolism produces heat internally. At the body surface, heat is exchanged with the environment by convection, radiation, conduction and evaporation. In humid environments, condensation of water vapour on the skin can become an additional inward heat flow. Respiration also contributes, but is usually smaller than the major exchanges at the skin.

A useful conceptual equation is:

Net heat storage = metabolic heat + convection + radiation + conduction + condensation − evaporation − other heat losses.

Each term can be positive or negative. If the surroundings are hotter than the skin, convection or radiation can carry heat into the body. If the skin is warmer than its surroundings, those same pathways can remove heat. Evaporation is special: as long as sweat can evaporate, it removes latent heat from the skin.

Why air temperature alone is a poor measure of thermal dose

Air is a relatively poor carrier of heat. Its density, heat capacity and thermal conductivity are low compared with liquid water. This is why a person can briefly tolerate air near 100 °C in a dry sauna, whereas immersion in water only a few degrees above body temperature can create a substantial and sustained heat load.

Humidity changes the picture because it controls evaporative cooling and, at sufficiently high vapour pressure, permits condensation. Radiant temperature matters because the body exchanges infrared radiation with all surrounding surfaces. Air movement matters because it alters convective and evaporative transfer. The thermal dose is therefore a property of the whole environment, not of temperature alone.

1. Finnish sauna: very hot air, but an important evaporative counterflow

In the Finnish sauna, the upper part of the cabin commonly reaches approximately 80–100 °C while the climate remains comparatively dry. Academy teaching material uses about 2–5% relative humidity at 100 °C as a representative dry-hot condition, corresponding to a water-vapour pressure of roughly 2–5 kPa. The walls, ceiling and benches are also hot, so the bather receives heat both by convection from the air and by long-wave thermal radiation from the surrounding surfaces. [1]

At the same time, sweating provides a powerful opposing heat flow. The vapour pressure at wet skin near body temperature is around 6.3 kPa at 37 °C. When the vapour pressure of the room air remains below that value, water can evaporate from the skin and remove heat. The dry-hot sauna is therefore characterised by simultaneous inward and outward heat flows: hot air and hot surfaces transfer heat toward the body, while evaporation transfers heat away. [1,2]

This explains an apparent paradox: the Finnish sauna can have the highest air temperature of all the bathing procedures discussed here without necessarily producing the greatest heat transfer per unit time. Its dryness preserves an important thermoregulatory escape route.

The Aufguss temporarily changes the Finnish sauna

An Aufguss raises the water-vapour content and vapour pressure of the cabin. Academy teaching material places the vapour pressure during an Aufguss around 4.1–9.1 kPa depending on the starting climate and water input. As the room-air vapour pressure approaches the vapour pressure at the wet skin, sweat evaporation is reduced. If it exceeds the local saturation condition at the cooler skin, sauna water can condense there. [1]

The heat sensation rises sharply even if air temperature does not rise. Two processes explain this: less heat is lost through evaporation, and condensation can release latent heat directly at the skin. The Aufguss therefore changes the heat balance mainly through water vapour, not through a sudden increase in air temperature.

2. Humid warm-air bath: lower temperature, smaller evaporative reserve

A humid warm-air bath operates at substantially lower temperatures than a Finnish sauna. A representative climate is approximately 50 °C and 50% relative humidity. The corresponding water-vapour pressure is about 6.2 kPa—already close to the saturation vapour pressure of wet skin at approximately 37 °C. [1]

Convective heat input is lower than in 90–100 °C sauna air because the air-to-skin temperature difference is much smaller. But the body's evaporative cooling capacity is also much smaller because the

vapour-pressure gradient between skin and environment has nearly disappeared. The result is a different thermal strategy: less extreme external temperature, but less opportunity to compensate by evaporation.

This is why a humid warm-air bath can feel surprisingly demanding despite its moderate air temperature. The lower sensible heat input is partly offset by the loss of evaporative heat dissipation.

3. Steam bath: condensation becomes a major heat-transfer pathway

In a steam bath, a representative climate is approximately 40–45 °C at or near 100% relative humidity. Academy teaching material uses 42 °C and a vapour pressure of approximately 8.2 kPa. That value is higher than the approximately 6.3 kPa saturation vapour pressure at 37 °C wet skin. [1]

Under these conditions, evaporation from the skin is severely restricted and water vapour can condense on the cooler body surface. This is thermally important because condensation releases the same latent heat that was previously required to vaporise the water. The visible film of water on the skin is therefore not simply sweat; part of it may be condensate from the room air.

The steam bath illustrates why 42 °C saturated air cannot be compared with 42 °C dry air. The temperature is modest, but the direction of the water-vapour heat exchange has changed. The body has lost evaporation as an effective cooling mechanism and can receive additional energy through condensation.

4. Infrared sauna: radiation replaces much of the hot-air load

Infrared cabins generally operate with lower air temperatures than Finnish saunas. Their defining feature is the deliberate use of infrared emitters directed toward the body. A larger fraction of environmental heat therefore reaches the skin by radiation rather than by first heating the room air.

Infrared radiation is conventionally divided into IR-A (0.78–1.4 µm), IR-B (1.4–3.0 µm) and IR-C (3.0 µm–1 mm). Which spectral regions dominate in an infrared cabin depends on emitter temperature and design. Hot full-spectrum or halogen emitters can produce relevant IR-A, IR-B and IR-C components, whereas lower-temperature ceramic and panel emitters shift emission toward longer wavelengths, especially IR-C.

The direct penetration of infrared radiation into tissue is wavelength-dependent. IR-A penetrates most deeply, reaching a few millimetres under favourable conditions. IR-B is absorbed more strongly and typically reaches approximately the millimetre range. IR-C is absorbed very strongly by water in the superficial skin and therefore deposits its radiant energy predominantly in the epidermis and uppermost tissue layers. Exact penetration depths are not fixed constants; they depend on wavelength, tissue composition and the definition of optical penetration depth.

This distinction is important because the common marketing term 'deep heat' can be misleading. Infrared radiation does not heat deep organs directly. The radiant energy is initially absorbed predominantly in the skin and superficial tissues. The resulting heat can subsequently be transported deeper by thermal conduction and, importantly, by increased cutaneous blood flow.

Because cabin air can remain cooler and relatively dry, convective heat input may be lower than in a Finnish sauna and evaporation can remain available. The total thermal dose therefore depends on irradiance, wavelength spectrum, emitter temperature, distance and orientation to the emitter, exposed body area, cabin air temperature and exposure time. Two infrared cabins with the same air temperature can consequently produce very different heat loads.

5. Warm-water bath: the most efficient surrounding heat-transfer medium

A warm-water bath may have the lowest environmental temperature in this comparison—often around 38–40 °C—yet water transfers heat far more effectively than air. Liquid water has a much higher volumetric heat capacity and thermal conductivity than air, and natural or forced water movement maintains contact between the skin and a large thermal reservoir. [5]

When most of the body is immersed, the skin is surrounded almost completely by the heat-transfer medium. Evaporation from immersed skin is impossible. If water temperature is above mean skin temperature, heat flows continuously from the water toward the body over a very large surface area. The small numerical temperature difference can therefore generate a substantial total heat input.

This is the key reason why a 40 °C bath cannot be considered 'mild' simply because 40 is far below 90 °C. The medium is different. A useful physical analogy is that 90 °C air contains little thermal mass per cubic metre, while liquid water in direct contact with the body can replace transferred energy continuously.

Comparing the dominant heat flows

The five bathing procedures can be understood by asking which heat-transfer pathways dominate:

- Finnish sauna: strong convection and radiation toward the body, opposed by substantial evaporative heat loss while the air remains dry.
- Humid warm-air bath: moderate convection and radiation, but markedly reduced evaporative cooling.
- Steam bath: moderate sensible heat transfer, almost no effective evaporation, plus potential latent heat gain through condensation.
- Infrared sauna: deliberately increased radiant heat transfer with comparatively less dependence on hot room air. IR-A, IR-B and IR-C may be present depending on the emitter; energy is absorbed mainly in skin and superficial tissue, then redistributed by conduction and blood flow. Evaporation often remains available.
- Warm-water bath: strong conductive/convective heat transfer from water over most of the immersed body surface, with no evaporative cooling from immersed skin.

Why there is no universal ranking in watts

It is tempting to assign each bathing procedure a single heat-transfer value in watts. Scientifically, that would be misleading without specifying the complete exposure. Heat flux changes continuously with skin temperature, sweating, air and water movement, surface temperatures, body position, immersed or exposed area, humidity, infrared irradiance and duration.

For example, convective heat transfer can be approximated as $q = h \times A \times (T_{environment} - T_{skin})$. But the heat-transfer coefficient h is very different in air and water and changes with flow. Radiant exchange depends on the fourth power of absolute surface temperatures. Evaporative heat loss depends on the vapour-pressure gradient and skin wettedness. Condensation reverses that latent heat flow. A physically meaningful comparison therefore requires a heat-balance model rather than a thermometer.

The decisive difference: sensible heat versus latent heat

Convection, conduction and radiation are often grouped as sensible heat transfer: energy moves because of temperature differences or electromagnetic radiation. Evaporation and condensation involve latent heat. For water, this phase-change energy is very large—around 2.4 MJ per kilogram near body temperature.

This is why humidity has such a disproportionate effect on thermal sensation. Only a small mass of water needs to evaporate from the skin to remove meaningful heat, and only a small mass of steam needs to condense to return meaningful heat. The difference between a dry sauna and a steam bath is therefore not merely 'how wet the air feels'; it changes one of the largest terms in the human heat balance.

What the vapour-pressure comparison tells us

The Academy's teaching comparison is particularly useful: wet skin at 37 °C has a saturation vapour pressure of about 6.3 kPa. Typical dry sauna air lies below this value at roughly 1.4–5.1 kPa, a humid warm-air bath lies around 6.1–6.2 kPa, and a saturated steam bath at 42 °C lies around 8.2 kPa. [1]

That sequence describes a thermophysiological transition. In the dry sauna, evaporation is generally possible. In the humid warm-air bath, the driving gradient becomes very small. In the steam bath, the environmental vapour pressure can exceed that at the cooler skin, favouring condensation. This is a more meaningful comparison of the three air-based bathing procedures than relative humidity alone.

Why 'hotter' does not mean 'more heat transferred'

The comparison leads to a fundamental principle: temperature is an intensive variable; transferred heat is an amount of energy. A very high temperature in a poor heat-transfer medium can deliver less energy than a much lower temperature in an efficient medium.

That is why a 90 °C sauna can be physiologically tolerable for a limited period, why 42 °C saturated steam can feel intensely hot, and why 40 °C water can continue warming the body despite appearing only slightly warmer than core temperature. The body experiences heat flux, not thermometer drama.

A conceptual order of thermal mechanisms—not a ranking of overall strain

The bathing forms can therefore be placed on two different axes rather than in a simple hottest-to-coldest list. One axis describes the physical pathway of heat input: from radiation-dominant infrared exposure through air-based convection/radiation to direct water contact. The second describes evaporative freedom: high in dry sauna or dry infrared conditions, progressively reduced in humid warm air, nearly absent in saturated steam, and absent from immersed skin in a water bath.

Overall physiological strain emerges from the combination of these axes with exposure time. A shorter, intense exposure and a longer, moderate exposure can produce similar total heat storage. For this reason, duration is part of the thermal dose just as much as temperature, humidity and heat-transfer medium.

Figure 1. Different heat baths – different heat-transfer mechanisms. The arrows illustrate dominant qualitative heat flows rather than exact quantitative fluxes. Infrared spectral composition depends on emitter design; IR-A penetrates deepest, IR-B less deeply, and IR-C is absorbed predominantly in superficial skin.

Conclusion

Finnish sauna, humid warm-air bath, steam bath, infrared sauna and warm-water bathing are not simply different temperatures of the same treatment. They are physically different heat-transfer systems.

The Finnish sauna combines intense convection and radiation with preserved evaporative cooling. Humid warm air progressively removes that cooling reserve. The steam bath can add latent heat through condensation. Infrared systems shift a larger part of the energy transfer toward radiation. Warm water places most of the body in direct contact with a highly effective heat-transfer medium and suppresses evaporation from the immersed surface.

The scientifically useful question is therefore not 'Which bath is hottest?' but 'Which heat flows act on the body, in which direction, over what surface area and for how long?' Only that heat-balance perspective explains why very different bathing climates can produce comparable—or very different—thermal loads.

References

[1] Gröning K. Das Saunabad und verwandte Badeformen. Teaching material, Deutsche Sauna-Akademie. Climate values and vapour-pressure comparison for Finnish sauna, humid warm-air bath and steam bath.

[2] Leppäluoto J. Human thermoregulation in sauna. Annals of Clinical Research. 1988;20(4):240–243.

[3] Hussain J, Cohen M. Clinical effects of regular dry sauna bathing: a systematic review. Evidence-Based Complementary and Alternative Medicine. 2018;2018:1857413. doi:10.1155/2018/1857413.

[4] Vatansever F, Hamblin MR. Far infrared radiation (FIR): its biological effects and medical applications. Photonics & Lasers in Medicine. 2012;1(4):255–266. doi:10.1515/plm-2012-0034. For infrared spectral classification and wavelength-dependent tissue absorption, see also standard photobiological literature on IR-A, IR-B and IR-C.

[5] Parsons K. Human Thermal Environments: The Effects of Hot, Moderate, and Cold Environments on Human Health, Comfort and Performance. 3rd ed. CRC Press; 2014.

[6] ISO 7933. Ergonomics of the thermal environment — Analytical determination and interpretation of heat stress using calculation of the predicted heat strain.

Editorial note: The examples describe characteristic physical mechanisms and representative bathing climates. They are not universal dose values. Actual heat transfer depends on the specific installation, surface temperatures, humidity, air or water movement, infrared irradiance, body position, exposed area, individual thermoregulation and exposure time.